

[Expert] How do I increase disk space on my Deskpro VM Appliance?

Phil Rigby - 2021-06-17 - Comments (0) - Troubleshooting

If you installed your Deskpro on-premise server using the **VM Appliance (OVA)**, then you would not have had the option to configure the virtual hardware during installation. By standard, the OVA requires a **64GB** disk, which will be adequate for the majority of users. However, if you have a larger helpdesk, or have been using the VM Appliance for a long time, you may find you are running out of disk space.

One of the options to resolve this issue is to increase the size of the disk on your Deskpro server. However, as it is running Linux, it is not as straight forward as increasing the size of the disk on your hypervisor. We would need to tell the server that the disk has increased and how to use it.

The guide below will walk you through the process of increasing the disk size on the Deskpro OVA.

Before you start:

This guide is specifically for **Ubuntu 16.04 LTS** and above. Older versions of the Deskpro OVA installed **Ubuntu 14.04 LTS** instead. At the time of writing, this version is past the [End of Standard Support, and is coming up to End of Life](#), so we highly recommend you update to a newer version. In this case, we recommend performing a [fresh OVA install](#), then increase the disk space on the new OVA following this guide. You can then migrate your old helpdesk over to your new helpdesk using the [dputils tool](#).

To find out what version of Ubuntu your OVA is using, login to the server via SSH, and run the following command:

```
cat /etc/os-release
```

We would also recommend disabling the helpdesk, by going to **Admin > Setup > Settings**, and checking the box marked **Disable the helpdesk**, before clicking **Save**. This should stop any changes being made or new tickets being processed during the procedure.

Once that's done, in your hypervisor, **clone the existing VM**, so you have a backup in case things go wrong, and then **increase the size of the disk** on the original VM.

Resizing the disk

On the VM, probe the hardware to see if it picks up the larger disk by running

```
partprobe
```

followed by

```
fdisk -l
```

to see if the disk has grown. You should be able to see that /dev/sda has increased, i.e, if you increase the disk to 100GB:

```
Disk /dev/sda: 100 GiB, 107374182400 bytes, 209715200 sectors
```

If this is still displaying the original size of 64GB, you will need to reboot the VM.

```
reboot
```

Once the server has booted back up, log back in and check fdisk.

```
fdisk -l
```

This should now display the new size of the disk /dev/sda at the top line.

However, the partition /dev/sda1 should still be set to 64GB

```
Device      Boot Start          End  Sectors  Size Id Type
/dev/sda1  *      2048 134215679 134213632  64G 8e Linux LVM
```

Resizing the partitions

As the OVA uses a swap partition, you'll need to turn that off

```
swapoff -a
```

Then, we'll need to go into parted to modify the partitions. First, open the parted prompt with

```
parted /dev/sda
```

Don't forget to set your units to sectors to make it easier to track.

```
(parted) u s
```

Then print the partition table so you have it available for reference:

```
(parted) p
```

```
Model: VMware Virtual disk (scsi)
```

```
Disk /dev/sda: 134217728s
```

```
Sector size (logical/physical): 512B/512B
```

```
Partition Table: msdos
```

```
Disk Flags:
```

```
Number  Start  End          Size          Type          File system  Flags
1       2048s  134215679s  134213632s   primary          boot, lvm
```

If your VM Appliance is running Ubuntu 16.04 or newer, then the default version of parted installed should support `resizepart`, which allows you to resize partitions. This option is unavailable for Ubuntu 14.04 and below, and requires you to delete and re-create the

partition, which if done incorrectly, can destroy your server's disks beyond recovery. If you are using Ubuntu 14.04, or the command below does not work, do **NOT** continue, and create a new OVA then migrate to that instead.

```
(parted) resizepart
Partition number? 1
End? [134215679s]? 100%
```

You're specifying the first partition on the partition table, and extending the partition to use 100% of the disk.

Now, when you print the partition table again, the output should be different:

```
(parted) p
Model: VMware Virtual disk (scsi)
Disk /dev/sda: 209715200s
Sector size (logical/physical): 512B/512B
Partition Table: msdos
Disk Flags:
Number  Start  End          Size          Type          File system  Flags
  1      2048s  209715199s  209713152s   primary              boot,
lvm
```

If this works, you should see the start sector is the same, but the end sector is much larger.

Once you're happy everything is correct, quit out of parted

```
(parted) quit
```

Then notify your kernel of the change

```
partprobe
```

You can confirm this is working by checking fdisk

```
fdisk -l
```

This should now show that the size of the partition now matches the size of the disk:

```
Device      Boot Start          End  Sectors  Size Id Type
/dev/sda1  *      2048 209715199 209713152 100G 8e Linux LVM
```

If not, you may need to reboot your server

```
reboot
```

If the server does not boot back up correctly, then an error was made when repartitioning the disk. This is extremely difficult to recover from, and may result in data loss. If this has happened to you, I recommend removing this VM and booting up the cloned VM which was made as a backup, then start again from the

beginning, including a fresh cloned VM to ensure you have the ability to fallback in the event of another error.

Resizing the Physical Volume

At this point, you should have extended your disk, and your partition should match. Now we need to extend the physical volume and logical volume for LVM, and finally the filesystem so the OS can use the additional space.

First, the physical volume.

```
pvdisplay
```

This should show the size of the physical volume defined in LVM, and should return something like this:

```
--- Physical volume ---
PV Name           /dev/sda1
VG Name           deskpro-vg
PV Size           <64.00 GiB / not usable 2.00 MiB
Allocatable       yes (but full)
PE Size           4.00 MiB
Total PE          16383
Free PE           0
Allocated PE      16383
PV UUID           SfqUax-akDv-3ucP-noxH-DUNZ-tJbq-7Cb0GE
```

This now needs to be resized with the following command:

```
pvresize /dev/sda1
```

Then to confirm it works, re-run the command again

```
pvdisplay
```

And you should now see that the PV size has increased:

```
--- Physical volume ---
PV Name           /dev/sda1
VG Name           deskpro-vg
PV Size           <100.00 GiB / not usable 2.00 MiB
Allocatable       yes (but full)
PE Size           4.00 MiB
Total PE          25599
Free PE           0
Allocated PE      25599
PV UUID           SfqUax-akDv-3ucP-noxH-DUNZ-tJbq-7Cb0GE
```

Extending the Logical Volume

Now, the logical volume. For this, we will need to find the mapper address for the logical volume. First, you need to confirm which logical volume is mounted as root.

```
df -h
```

This should give an output similar to this:

Filesystem	Size	Used	Avail	Use%	Mounted on
udev	972M	0	972M	0%	/dev
tmpfs	199M	9.4M	190M	5%	/run
/dev/mapper/deskpro--vg-root	62G	4.9G	54G	9%	/
tmpfs	994M	0	994M	0%	/dev/shm
tmpfs	5.0M	0	5.0M	0%	/run/lock
tmpfs	994M	0	994M	0%	/sys/fs/cgroup
tmpfs	199M	0	199M	0%	/run/user/0

What you need to do is look at the last column first for root (/), then check the first column to see what filesystem is mounted. For this example, it is /dev/mapper/deskpro--vg-root (note the double hyphen between deskpro and vg).

This is the logical volume that needs to be extended. You can do that with the following command:

```
lvextend -l +100%FREE /dev/mapper/deskpro--vg-root
```

This should extend the logical volume to use up the remaining space on the partition. You can confirm this has worked by checking fdisk

```
fdisk -l
```

It should now display that logical volume with the new volume size:

```
Disk /dev/mapper/deskpro--vg-root: 99 GiB, 106342383616 bytes,
207699968 sectors
```

```
Units: sectors of 1 * 512 = 512 bytes
```

```
Sector size (logical/physical): 512 bytes / 512 bytes
```

```
I/O size (minimum/optimal): 512 bytes / 512 bytes
```

Resizing the File System

Now, we can increase the filesystem to make this extra space usable with the following command:

```
resize2fs /dev/mapper/deskpro--vg-root
```

Once this has completed, your VM should now be able to use the additional space. You can confirm this with the following command:

```
df -h
```

This should now show that the size of the `/dev/mapper/deskpro--vg-root` filesystem mounted on `/` has a larger size, and is no longer 100% used.

Filesystem	Size	Used	Avail	Use%	Mounted on
udev	972M	0	972M	0%	/dev
tmpfs	199M	9.4M	190M	5%	/run
/dev/mapper/deskpro--vg-root	98G	4.9G	88G	6%	/
tmpfs	994M	0	994M	0%	/dev/shm
tmpfs	5.0M	0	5.0M	0%	/run/lock
tmpfs	994M	0	994M	0%	/sys/fs/cgroup
tmpfs	199M	0	199M	0%	/run/user/0

Reopening your Helpdesk

The disk upgrade should now be finished. Don't forget to turn swap back on

```
swapon
```

Now, you should be able to log back into your helpdesk and re-enable it, by going to **Admin** > **Setup** > **Settings**, and unchecking the box marked **Disable the helpdesk**, then clicking **Save**.